

100% Real Avaya 3204 Brain Dumps From Lead2pass With New Added Questions For Free Download

100% valid 3204 brain dumps with more new added questions. By training the Lead2pass Avaya 3204 77q questions, you will save a lot time in preparing the exam. Visit www.lead2pass.com to get the 100% pass ensure!

QUESTION 1 Of the three Media Server roles, which Role is used to prompt for conference codes? A. IVRB. HostingC. CascadingD. ANNC Answer: A Explanation: http://portaone.com/resources/docs/PortaSIP/m-r-45/PortaSIP_Media_Server_MR45.pdf (See the Page #8, 1ST Paragraph).

QUESTION 2 Under which condition will a redundant conferencing application server failover? A. If the active Avaya Aura Conferencing database is unreachableB. If the Media Server is unreachableC. If the firewall blocked the signaling serverD. If the primary application server stops communicating with the standby application server Answer: A

QUESTION 3 What is the script that is used to install Avaya Aura Conferencing software? A. InstallmcpB. pkginstallC. aacInstallerD. mcpInstaller Answer: D Explanation: Avaya Media Server: The Avaya Aura Conferencing application requires one or more Avaya Media Servers for media processing. The mcpInstaller script can install the media server automatically in all (SMB, medium, and large) configurations. If you are implementing a redundant deployment, the mcpInstaller automatically installs a primary and a secondary Avaya Media Server. <https://downloads.avaya.com/css/P8/documents/100182326>

QUESTION 4 You are installing the operating system for Avaya Aura Conferencing and you turn on the hardware to start the installation. What must you then do at the boot prompt? A. type startinstallB. press the Enter keyC. type install-kvm and press the Enter keyD. type install-mcp and press the Enter key Answer: C Explanation: 1. Insert the AAC Platform DVD-ROM, and reboot the server. The following message on the installation welcome screen appears: Welcome to the MCP Core Linux System Installer 2. At the boot prompt, type install-kvm, and press Enter. 3. To check the integrity of the system, type y, and press Enter <https://downloads.avaya.com/css/P8/documents/100182326>

QUESTION 5 Where can you modify the alert threshold settings for the Avaya Aura Conferencing? A. Monitoring and ReportingB. Key Performance IndicatorsC. OAM ProfilesD. Feature Server Elements Answer: B Explanation: <https://downloads.avaya.com/css/P8/documents/100182324> (See the Page #50).

QUESTION 6 What does the extension .active at the end of the log file name indicate? A. The log is currently closed.B. The log is the most recent log file.C. The log has been previously opened.D. The log is obsolete. Answer: D

QUESTION 7 You want to find the thresholds configured in the system for minor, major, and critical alarms for Jitter (ms) on the Element Manager. Under which folder are the Alert Thresholds found? A. Log FiltersB. Media Servers and ClustersC. Key Performance IndicatorsD. Application Servers Answer: A

The Lead2pass Avaya 3204 77q in PDF and VCE that we have is for free now, and all has been updated by Avaya professionals. All the new 3204 exam questions and answers are added in the new version. Visit the site to get more free information.

<http://www.lead2pass.com/3204.html>